

AUCTeX Reference Card

(for version 11.82)

Conventions Used

Carriage Return or C-m	RET
Tabular or C-i	TAB
Linefeed or C-j	LFD

Shell Interaction

Run a command on the master file	C-c C-c
Run a command on the buffer	C-c C-b
Run a command on the region	C-c C-r
Fix the region	C-c C-t C-r
Kill job	C-c C-k
Recenter output buffer	C-c C-l
Next error in TeX/LaTeX session	C-c '
Toggle debug of wonderful boxes	C-c C-w
View output file	C-c C-v

Commands you can run on the master file (with C-c C-c) or the region (with C-c C-r) include the following (starred versions are not available in all modes):

TeX	*TeX
LaTeX	*LaTeX
ConTeXt (once)	*ConTeXt
ConTeXt Full	*ConTeXt Full
Makeinfo	*Makeinfo
Makeinfo with HTML output	*Makeinfo HTML
Appropriate previewer	View
Print the output	Print
BibTeX	BibTeX
MakeIndex	Index
LaCheck	Check
Make (PostScript) File	File
Ispell	Spell

TeXing options

TeX runs can come in various types, which may be toggled and are indicated in the mode line.

Ω mode	C-c C-t C-o
PDF/DVI mode	C-c C-t C-p
Stop on errors (Interactive mode)	C-c C-t C-i
Use Source Specials for viewer control	C-c C-t C-s

Miscellaneous

Read AUCTeX manual	C-c TAB
Math Mode	C-c ~
Reset Buffer	C-c C-n
Reset AUCTeX	C-u C-c C-n

Multifile Handling

Save Document	C-c C-d
Switch to master file or active buffer	C-c ^
Query for a master file	C-c _

Command Insertion

Insert Section	C-c C-s
Insert L ^A T _E X environment	C-c C-e
Insert item	C-c LFD
Insert item (alias)	M-RET
Close L ^A T _E X environment	C-c]
Insert T _E X macro \{ }	C-c C-m
Insert double brace	C-c {
Complete T _E X macro	M-TAB
Smart “quote”	"
Smart “dollar”	\$

Font Selection

Insert bold text	C-c C-f C-b
Insert <i>italics</i> text	C-c C-f C-i
Insert roman text	C-c C-f C-r
Insert <i>emphasized</i> text	C-c C-f C-e
Insert <i>typewriter</i> text	C-c C-f C-t
Insert slanted text	C-c C-f C-s
Insert SMALL CAPS text	C-c C-f C-c
Delete font	C-c C-f C-d
Replace font	C-u C-c C-f ⟨key⟩

Source Formatting

Indent current line	TAB
Indent next line	LFD
Format a paragraph	M-q
Format a region	C-c C-q C-r
Format a section	C-c C-q C-s
Format an environment	C-c C-q C-e
Mark an environment	C-c .
Mark a section	C-c *
Comment or uncomment region	C-c ;
Comment or uncomment paragraph	C-c %

Copyright © 1987, 93, 2004, 05 Free Software Foundation, Inc.
Copyright © 1992 Kresten Krab Thorup
for AUCTeX version 11.82

Permission is granted to make and distribute copies of this card provided the copyright notice and this permission notice are preserved on all copies.

Math Mode

Variables

All math mode commands are under the prefix key specified by LaTeX-math-abbrev-prefix, default is “”.

You can define your own math mode commands by setting the variable LaTeX-math-list before loading LaTeX-math-mode.

Greek Letters

α	(\alpha)	α	ν	(\upsilon)	υ
β	(\beta)	β	ϕ	(\phi)	φ
γ	(\gamma)	γ	χ	(\chi)	χ
δ	(\delta)	δ	ψ	(\psi)	ψ
ε	(\epsilon)	ε	ω	(\omega)	ω
ζ	(\zeta)	ζ	Δ	(\Delta)	Δ
η	(\eta)	η	Γ	(\Gamma)	Γ
θ	(\theta)	θ	Θ	(\Theta)	Θ
κ	(\kappa)	κ	Λ	(\Lambda)	Λ
λ	(\lambda)	λ	Ξ	(\Xi)	Ξ
μ	(\mu)	μ	Π	(\Pi)	Π
ν	(\nu)	ν	Σ	(\Sigma)	Σ
ξ	(\xi)	ξ	Υ	(\Upsilon)	Υ
π	(\pi)	π	Φ	(\Phi)	Φ
ρ	(\rho)	ρ	Ψ	(\Psi)	Ψ
σ	(\sigma)	σ	Ω	(\Omega)	Ω
τ	(\tau)	τ			

Symbols

→	(\rightarrowarrow)	C-f	⊇	(\supseteqq)]
←	(\leftarrowarrow)	C-b	∅	(\emptysetset)	0
↑	(\uparrowarrow)	C-p	\	(\setminus)	\
↓	(\downarrowarrow)	C-n	∪	(\cup)	+
≤	(\leqq)	<	∩	(\cap)	-
≥	(\geqq)	>	{	(\langle)	(
˜	(\tilde)	~	}	(\rangle))
∇	(\nabla)	N	exp	(\exp)	C-e
∞	(\infty)	I	sin	(\sin)	C-s
∀	(\forallall)	A	cos	(\cos)	C-c
∃	(\existsists)	E	sup	(\sup)	C-^
/	(\not)	/	inf	(\inf)	C-_
∈	(\in)	i	det	(\det)	C-d
×	(\times)	*	lim	(\lim)	C-l
·	(\cdot)	.	tan	(\tan)	C-t
⊂	(\subsetset)	‡	‡	(\hat)	^
⊃	(\supsetset)	}	∨	(\vee)	
⊆	(\subseteqq)	[∧	(\wedge)	&

Miscellaneous

cal letters c ⟨letter⟩

preview-latex

Activation

preview-latex is part of AUCTeX. If it is active, you should see an entry “Preview” in the menu bar when editing L^AT_EX files. If you have a “LaTeX”, but no “Preview” menu, add the following to your `.emacs` file:

```
(load "preview-latex.el" nil t t)
```

Usage and keybindings

preview-latex operation only affects the display of the buffer, not its contents. It runs only on demand, using the target DVI or PDF files in the process. The first command in the following list (also on the toolbar button) will (as applicable) repreview an active region or a single modified preview, toggle the visibility of an unmodified preview or generate previews for a surrounding buffer area up to the next preview.

Preview at point	C-c C-p C-p
Preview environment	C-c C-p C-e
Preview region	C-c C-p C-r
Preview buffer	C-c C-p C-b
Preview document	C-c C-p C-d
Remove previews at point	C-c C-p C-c C-d
Remove previews from region	C-c C-p C-c C-r
Remove previews from buffer	C-c C-p C-c C-b
Remove previews from document	C-c C-p C-c C-d
Cache preamble	C-c C-p C-f
Switch off preamble cache	C-c C-p C-c C-f
Read Texinfo manual	C-c C-p TAB
Copy region as MML	C-c C-p C-w

The last keysequence will copy a region with previews into the kill buffer in a form fit for sending in Emacs’ message-mode.

Customization within Emacs

You can use M-x `customize-variable` RET or the “Preview/Customize” menu for customization. Worthwhile settings:

If you have dvipng available:	
Set to dvipng	preview-image-type
Keep counter values when regenerating single previews:	
Set to t	preview-preserve-counters
Cache/Don’t cache preamble without query (preamble caching is done using <code>mylatex.ltx</code> and might not always work. Use the appropriate key sequences for overriding the following setting):	
Set to t/nil	preview-auto-cache-preamble

Customization from L^AT_EX

Customization is done in the document preamble (you need to load `preview.sty` explicitly) or in `prauctex.cfg` (which should load the system `prauctex.cfg` first). Commands:

Preview macro	\PreviewMacro[{\{args\}}]{\{macro\}}
Preview env	\PreviewEnvironment[{\{args\}}]{\{env\}}
Skip macro	\PreviewMacro*[{\{args\}}]{\{macro\}}
Skip env	\PreviewEnvironment*[{\{args\}}]{\{env\}}

Diverting material from float environments

Snarf stuff	\PreviewSnarfEnvironment[{\{args\}}]{\{env\}}
-------------	---

Values to be used within `<args>`:

Optional argument	[]
Mandatory argument	{}
Optional star	*

Conditionals	?{\{token\}}{\{if found\}}{\{if not found\}}
--------------	--

Skip next token	-
-----------------	---

Transformation	#{\{macro args\}}{\{replacement\}}
----------------	------------------------------------

More options and explanations can be found in `preview.dvi` or the Texinfo manual.

Folding Source Display

Toggle folding mode	C-c C-o C-f
Hide all items in buffer	C-c C-o C-b
Hide all items in region	C-c C-o C-r
Hide all items in paragraph	C-c C-o C-p
Hide current macro	C-c C-o C-m
Hide current environment	C-c C-o C-e
Show all items in buffer	C-c C-o b
Show all items in region	C-c C-o r
Show all items in paragraph	C-c C-o p
Show current item	C-c C-o i
Hide or show current item	C-c C-o C-o

RefTeX

Activation

RefTeX is part of [X]Emacs. To activate and make it interact with AUCTeX, insert the following lines in `.emacs`.

```
(add-hook 'latex-mode-hook 'turn-on-reftex)
(add-hook 'LaTeX-mode-hook 'turn-on-reftex)
(setq reftex-plug-into-auctex t)
```

Table of Contents

The table of contents is a structured view of the entire document. It contains the sections, and optionally labels, index entries, and file boundaries.

```
Show the table of contents1 C-c =
Recenter *toc* buffer to here1 C-c -
```

Crossreferences, Citations, Index

Insert unique label ¹	C-c (
Reference a label ¹	C-c)
Insert citation with key selection	C-c [
... prompt for optional arguments	C-u C-c [
Index word at point with default macro	C-c /
Insert an index entry	C-c <
Add word to index phrases	C-c \
Visit index phrases buffer	C-c
Compile and display index	C-c >
View cross reference ¹	C-c &
View cross reference with mouse	S-mouse-2
View cross reference from BibTeX file	C-c &

Standard keys in special buffers

RefTeX’s special buffers have many active keys. The common ones are:

Display summary of active keys	?
Select this item	RET
Rescan the document	r
Display location in other window	SPC
Follow mode	f

Multifile actions

Since RefTeX scans the entire (multifile) document, it can provide commands that act on all files of a document. Check the `Ref->Global Actions` menu for these commands.

Variables

To tell reftex about your own macro definitions, customize the variables

```
reftex-label-alist
reftex-section-levels
reftex-index-macros
reftex-cite-format
```

¹ An argument of `C-u` triggers a document scan first. This can be necessary if file content and RefTeX’s knowledge are no longer consistent.